

Finacle Support brings you this fortnightly knowledge bulletin to augment your problem-solving capability. Every edition is put together with utmost diligence to ensure that best practices and known resolutions are shared. In this edition, you will find the following articles:

- IN_MEM_POSTING_REQD Parameter Posting at Connect-24
- How to Split the Swift Messages Separately Using SWIFT_NUM_OF_MSG_PER_FILE Parameter
- Build Finacle Expertise with the Knowledge Base on FSC

So let's start reading!

IN_MEM_POSTING_REQD Parameter in Connect-24

Product: Connect 24 Version: 10.2.x

In-Memory Posting is a parameter that allows accumulating transactions and posting at a later point in time. There are multiple C-24 transactions like **CWDR**, **CDAR**, and **TRDR**- where customer accounts are present in one part transaction, while contra accounts are present in the other. For example, in a **CWDR** request, the debit leg on Field 102 (Debit Foracid) and the credit leg on Contra Account are generally posted simultaneously.

The env parameter **IN_MEM_POSTING_REQD** set in the **start-uniser** file determines the posting mode which can be **Normal** or **In-Memory**. If the env parameter is set to **'Y'** (in the start-uniser file), only the debit leg is posted In-Memory during transaction processing and a single credit occurs to the contra account after a limit is reached for the number of debit transactions.



This limit is determined by the env CDCI_MAX_NUM_MSGS_PER_TRAN (default value is 300) set in uniser.cfg file.

i.e., if **CDCI_MAX_NUM_MSGS_PER_TRAN** is set as say 400, then there will be 400 customer debit part trans (on customer Accounts) and one consolidated contra part tran (on Contra Account). This process is controlled by a separate service called **Fincron**.

By default, the value of this parameter is set to '**Y**'. If the bank has enabled async posting feature for contra accounts (refer to the article on the Asynchronous Balance Update Feature for Office Accounts <u>here</u>), it is advised to set this parameter as '**N**'. To change it to '**N**', export the following in the start-uniser file (/uniser/bin directory OR /uniser/fce directory) and restart the services

IN_MEM_POSTING_REQD = N export IN_MEM_POSTING_REQD

How to Split the Swift Messages Separately Using SWIFT_NUM_OF_MSG_PER_FILE Parameter *Product: Finacle Core Banking Version: 10.x onwards*



Whenever SWIFT messages are transmitted, users can view the messages in the logs directory. All messages are generated in one MSG file, and users may find it difficult to traverse through the messages. To solve this problem, Finacle has introduced a parameter **SWIFT_NUM_OF_MSG_PER_FILE** to specify the number of SWIFT messages per file. This parameter can be set in the **paymentsys.dat file** in **\$B2K_SECURE_DIR/FINCORE/<barbon set**.

For example, SWIFT_NUM_OF_MSG_PER_FILE = 20, specifies that an MSG file will contain 20 SWIFT messages.

Build Finacle Expertise with the Knowledge Base on FSC Finacle Support Center has an expansive library of Troubleshooting Documents (TSD) curated by experts that not only give detailed solutions to problems but also aid in building your Finacle expertise. Let us look at an example with one of the latest documents uploaded to FSC- Enabling IE Mode in MS Edge. Self-help from Finacle Support Center > Search Results Enabling IE Mode in MS Edge Sources IE Mode in MS Edge GuideLine.pdf Down oad IE Mode in MS Edge GuideLine.pdf Finacle Core Banking Solution IE Mode in MS Edge Guide 27 Jun 2021 © 2021 EdgeVerve Systems Limited. Strictly private... TechOnline Resolution (12647) FAQ (1682) Module: CORE Product: FINACLE CORE BANKING Version: 11.X Menu Lexicon (710) FAQ for Enabling IE Mode in Ms Edge Download FAQ for Enabling IE Mode in Ms Edge Troubleshooting Documents Finacle Troubleshooting Documents Page 1 of 8 | EdgeVerve Systems Limited – Internal Frequently Asked Questions for Enabling IE Mode in MS Edge Troubleshooting Documents... (165) Module: GENERAL Product: FINACLE CORE BANKING Version: 10.X Finacle Support Connect (60) IE Mode in MS Edge_Webinar.pdf Download IE Mode in MS Edge_Webinar.pdf Finacle Webinars (28) 100+ countries | Over a billion people | 1.7 billion accounts Inspi ng Better Banking Finacle Micro Learni ww.finacle.com Better Inspires Better Webinar on IE Mode in MS Edge 2 | ©2022 EdgeVerve... Finacle Support Center (3) Module: CORE Product: FINACLE CORE BANKING Version: 11.X User searches for "Enabling IE Mode in MS Edge" → Selects 'Troubleshooting FINACLE **Documents'** SUPPORT CENTER The results will show TSDs explaining the guidelines as well as FAQs on how to enable IE mode on MS Edge. Separate guides for Finacle Core Banking versions 10.x and 11.x are also available on the portal. Pair these with the webinar recordings conducted by our experts, and you now have a full understanding of this concept.

Visit the **FSC portal** today to get more insights on Finacle!

Do you have the most useful Finacle URLs handy? Bookmark these Finacle links:

- Finacle Support Center: <u>https://support.finacle.com/</u>
- Finacle Knowledge Center: <u>https://content.finacle.com</u>
- TechOnline: https://interface.infosys.com/TechonlineV2/base/globallogin

Hope you like this edition. Is there anything that you'd like to see in the forthcoming series? We'd love to hear from you! Write to us at <u>finaclesupport@edgeverve.com</u>



Better Inspires Better

www.finacle.com

External - Confidential

Finacle Digital Communication Services

Copyright © 2022 EdgeVerve Systems Limited